### Quick Links | ieZoom home | Print Web | Quick tour | Screenshots | Skins | Online help | FAQ | Buy now | Download



When printing a web page using IE (Internet Explorer), there is page information printed in each page header (the top of printed page) and footer (the bottom of printed page). The information in the header and footer may vary for different web browsing software, but usually it includes the web page title, web page address (URL), the current page number, total number of pages and the date of printing.

Depending on the tasks you are solving by printing web page, there might be a necessity to include additional or remove unnecessary information from the header and footer. Internet Explorer allows to configure header / footer information (by using IE printing codes), or alternatively remove header and footer information completely.

| Code       | Description   | Preview                         |    |       |
|------------|---|---------------------------------|----|-------|
| &w         | Window title.   | Internet Explorer header / foot |    |       |
| &u         | Page <u>address</u> (URL).  | http://www.febooti.com/produc   |    |       |
| &d         | Date in short format specified by Regional Settings.                    | 10/24/2009                      |    |       |
| &D         | Date in long format specified by Regional Settings.                     | Saturday, October 24, 2009      |    |       |
| &t         | Time in the format specified by Regional Settings.                      | 6:57:52 PM                      |    |       |
| &T         | Time in <u>24-hour</u> format.  | 18:57:52 P                      | М  |       |
| &р         | Current page number.  | 1                               |    |       |
| &P         | <u>Total number</u> of pages.   | 2                               |    |       |
| &&         | A single <u>ampersand</u> : &.  | &                               |    |       |
| &b         | Separates preceding and following text into different <u>sections</u> . | Left                            | &b | Right |
| Text && &p | <u>Custom text</u> (can be used in combination with printing codes).    | Text & 1                        |    |       |
|            | Nothing - removes IE header and / or footer completely.                 |                                 |    |       |



To <u>configure print</u> header / footer, click *File*, select *Page Setup* and enter appropriate codes (special characters) into **Headers and Footers** section. Note that Internet Explorer header / footer codes are case sensitive.

### Look closer

Febooti Automation Workshop automate and schedule recurring tasks, and automated processes Febooti Command line email utility send email directly from DOS command line (MS-DOS prompt) Febooti fileTweak - change file date, time and attributes

# How to?

What is Adobe Acrobat (pdf.ocx) compatibility bug
How to use toolbar skins options
How to use toolbar tweaks options

## Links

Link to us! Links

#### Choose one of options below:

Did you find this page useful? Help us improve the content. Take our quick survey! E-mail this page.

#### Rate the quality of this content:



**NOTE!** Your answers will be completely anonymous unless you deliberately add your e-mail address.

By offering suggestions on this page, you give Febooti Software full permission to implement them on website.

Terms | Privacy statement | Add bookmark | Search | Site map